

Thank you for using the Renesas Electronics integrated development environment.  
This document describes restrictions and points for caution on using this product. Read this document before using the package.

### Contents

Chapter 1. User's Manuals .....	2
Chapter 2. Operating Environment.....	3
Chapter 3. Improvements and Changes.....	4
Chapter 4. Installation.....	5
Chapter 5. Uninstallation .....	6
Chapter 6. Points for Caution .....	7
Revision Record .....	9

## Chapter 1. User's Manuals

Please read the following user's manuals along with this document.

The stated version numbers may differ from that of the product depending on whether the user's manuals have been revised.

Manual Name	Document Number
License Manager V2.09.00 User's Manual	R20UT5725EJ0100
License Manager V2.09.00 (for Linux) User's Manual	R20UT5727EJ0100
Software for Floating License Management V2.09.00 User's Manual	R20UT5726EJ0100
Software for Floating License Management V2.09.00 (for Linux) User's Manual	R20UT5728EJ0100

## Chapter 2. Operating Environment

### 2.1 Hardware environment

- Processor and main memory that provide a comfortable user experience of the software described in section 2.2, Software environment
- Display: Resolution at least 1,024 x 768 (recommended 1920 x 1080)

### 2.2 Software environment

#### OS

- Windows 10
- Windows 11

#### Runtime Library

- Microsoft .NET Framework 4.8

#### Software for Floating License Management

- Software for Floating License Management V2.08.00 or later
- Software for Floating License Management V2.08.00 (for Linux) or later

## Chapter 3. Improvements and Changes

This chapter describes the main changes in the license manager from V2.08.00 to V2.09.00.

### 3.1 Updating the operating environment

The software environment for running the license manager has been updated.

### 3.2 Improvement to the operation when an error (E0172009) may be displayed while launching the license manager

In some cases, launching of the license manager V2.08.00 (for Windows) would not succeed due to a displayed error (E0172009). However, this operation has now been corrected.

### 3.3 Changes to the floating license (offline mode)

For the floating license (offline mode), functionality has been added and the operation has been improved in the ways described below.

- When a floating license (offline mode) is in use, a function for indicating the current state of using the floating license has now been added to the license manager.
- When a floating license (offline mode) is forcibly terminated by the software for floating license management, the operation has now been improved so that the license is also invalidated on the license manager side.

## Chapter 4. Installation

Run the CS+ integrated installer (file name: CSPlus\_CC\_Package\_VXXXXX.EXE or CSPlus\_CACX\_Package\_VXXXXX.EXE) or the stand-alone installer for the license manager (file name: RenesasLicenseManager\_VXXXXX.exe).

## Chapter 5. Uninstallation

You can uninstall a license manager by selecting [Renesas MCU Tools License Manager] from [Apps & features] or [Installed apps] in [Settings] of Windows.

## Chapter 6. Points for Caution

### 6.1 Points for caution regarding installation

#### 6.1.1 Administrator privileges

Windows administrator privileges are required to install the software.

#### 6.1.2 Execution environment

The Microsoft .NET Framework is required to run the installer. If the Microsoft .NET Framework is not installed, the CS+ integrated installer will install it.

#### 6.1.3 Starting the installer

If the installer is started under a non-Japanese version of Windows and the path for starting the installer includes multi-byte characters, an error will occur and the installer will not start.

#### 6.1.4 Network drives

The software cannot be installed from a network drive.  
It also cannot be installed to a network drive.

#### 6.1.5 Installation folder name

The available characters for specifying the installation folder are the same as for Windows.  
The 12 characters / \* : < > ? | " \ ; , # and %nn (n:number of hexadecimal) cannot be used. Folder names also cannot start or end with a space.

#### 6.1.6 Required files after installation

The following folder is created after installation. Do not delete it, because it contains files that are necessary for the tools to run.

(32-bit Windows, and installation drive is C:)

C:\Program Files\Common Files\Renesas Electronics MCU Tools\

(64-bit Windows, and installation drive is C:)

C:\Program Files (x86)\Common Files\Renesas Electronics MCU Tools\

#### 6.1.7 Modifying and repairing functions

To modify or repair the function of a tool that has already been installed, have the tool's installer package on hand, and run the installation program. The program maintenance program will start; select **Modify** or **Repair**.

Clicking on [Apps & features] from [Settings] of Windows or [Programs and Features] of the control panel will cause an error.

#### 6.1.8 Changing the installation folder

To change the folder that tools are installed to, you must first uninstall all tools, and then perform installation again.

#### 6.1.9 Version of installed tools

If the newer version tool is already installed, the older version tool may not be installed.

## 6.2 Points for caution regarding uninstallation

### 6.2.1 Administrator privileges

Windows administrator privileges are required to uninstall the software.

### 6.2.2 Uninstallation folder name

Depending on the order in which tools are uninstalled, the folders may not be completely deleted. If this happens, remove any remaining folders via Explorer or the like.

### 6.2.3 Adding/repairing via other than the installer

If you added or modified files to the folders in which tools and release notes were installed using other means than the installers, they cannot be deleted during uninstallation.

### 6.2.4 Microsoft Tools

Uninstall the Microsoft .NET Framework, separately from the license manager by using [Apps & features] or [Installed apps] in [Settings] of Windows.

## 6.3 Notes on updating the version

### 6.3.1 Updating the version of the software for floating license management

Software for floating license management V2.08.00 or a later version is required to use floating licenses with license manager V2.09.00. If you will be using a floating license, update the version of the software for floating license management by downloading it from the Web page for the given compiler package.

[C Compiler Package for RL78 Family \[CC-RL\] – Downloads](#)

[C/C++ Compiler Package for RX Family \[CC-RX\] – Downloads](#)

[C Compiler Package for RH850 Family \[CC-RH\] – Downloads](#)

### 6.3.2 Floating license (Offline Mode)

If you update the license manager from V2.08.00 or an earlier version to V2.08.00 or a later version, the "Floating License (Offline Mode)" that the license manager obtained from the software for floating license management will be invalidated.

If you want to continue to use the "Floating License (Offline Mode)", force leaving the "Floating License (Offline Mode)" using the Software for floating license management and re-get the "Floating License (Offline Mode)" from the Software for floating license management using the license manager.

### 6.3.3 Updating the version from floating license client V1.00.00

If you update the version from floating license client V1.00.00 to license manager V2.00.00 or a later version, the setting for using the floating license will be disabled by default. To use the floating license, enable the setting according to the following procedure.

Click on the [Option] button in the [License Manager] window, and then click on the [Enable] button in the [Floating License Option] dialog box.

### Revision Record

Rev.	Date	Description	
		Page	Summary
1.00	Sep 01, 2025	-	First Edition issued

## Notice

1. Descriptions of circuits, software and other related information in this document are provided only to illustrate the operation of semiconductor products and application examples. You are fully responsible for the incorporation or any other use of the circuits, software, and information in the design of your product or system. Renesas Electronics disclaims any and all liability for any losses and damages incurred by you or third parties arising from the use of these circuits, software, or information.
2. Renesas Electronics hereby expressly disclaims any warranties against and liability for infringement or any other claims involving patents, copyrights, or other intellectual property rights of third parties, by or arising from the use of Renesas Electronics products or technical information described in this document, including but not limited to, the product data, drawings, charts, programs, algorithms, and application examples.
3. No license, express, implied or otherwise, is granted hereby under any patents, copyrights or other intellectual property rights of Renesas Electronics or others.
4. You shall be responsible for determining what licenses are required from any third parties, and obtaining such licenses for the lawful import, export, manufacture, sales, utilization, distribution or other disposal of any products incorporating Renesas Electronics products, if required.
5. You shall not alter, modify, copy, or reverse engineer any Renesas Electronics product, whether in whole or in part. Renesas Electronics disclaims any and all liability for any losses or damages incurred by you or third parties arising from such alteration, modification, copying or reverse engineering.
6. Renesas Electronics products are classified according to the following two quality grades: "Standard" and "High Quality". The intended applications for each Renesas Electronics product depends on the product's quality grade, as indicated below.

"Standard": Computers; office equipment; communications equipment; test and measurement equipment; audio and visual equipment; home electronic appliances; machine tools; personal electronic equipment; industrial robots; etc.

"High Quality": Transportation equipment (automobiles, trains, ships, etc.); traffic control (traffic lights); large-scale communication equipment; key financial terminal systems; safety control equipment; etc.

Unless expressly designated as a high reliability product or a product for harsh environments in a Renesas Electronics data sheet or other Renesas Electronics document, Renesas Electronics products are not intended or authorized for use in products or systems that may pose a direct threat to human life or bodily injury (artificial life support devices or systems; surgical implantations; etc.), or may cause serious property damage (space system; undersea repeaters; nuclear power control systems; aircraft control systems; key plant systems; military equipment; etc.). Renesas Electronics disclaims any and all liability for any damages or losses incurred by you or any third parties arising from the use of any Renesas Electronics product that is inconsistent with any Renesas Electronics data sheet, user's manual or other Renesas Electronics document.

7. No semiconductor product is absolutely secure. Notwithstanding any security measures or features that may be implemented in Renesas Electronics hardware or software products, Renesas Electronics shall have absolutely no liability arising out of any vulnerability or security breach, including but not limited to any unauthorized access to or use of a Renesas Electronics product or a system that uses a Renesas Electronics product. RENASAS ELECTRONICS DOES NOT WARRANT OR GUARANTEE THAT RENASAS ELECTRONICS PRODUCTS, OR ANY SYSTEMS CREATED USING RENASAS ELECTRONICS PRODUCTS WILL BE INVULNERABLE OR FREE FROM CORRUPTION, ATTACK, VIRUSES, INTERFERENCE, HACKING, DATA LOSS OR THEFT, OR OTHER SECURITY INTRUSION ("Vulnerability Issues"). RENASAS ELECTRONICS DISCLAIMS ANY AND ALL RESPONSIBILITY OR LIABILITY ARISING FROM OR RELATED TO ANY VULNERABILITY ISSUES. FURTHERMORE, TO THE EXTENT PERMITTED BY APPLICABLE LAW, RENASAS ELECTRONICS DISCLAIMS ANY AND ALL WARRANTIES, EXPRESS OR IMPLIED, WITH RESPECT TO THIS DOCUMENT AND ANY RELATED OR ACCOMPANYING SOFTWARE OR HARDWARE, INCLUDING BUT NOT LIMITED TO THE IMPLIED WARRANTIES OF MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE.
8. When using Renesas Electronics products, refer to the latest product information (data sheets, user's manuals, application notes, "General Notes for Handling and Using Semiconductor Devices" in the reliability handbook, etc.), and ensure that usage conditions are within the ranges specified by Renesas Electronics with respect to maximum ratings, operating power supply voltage range, heat dissipation characteristics, installation, etc. Renesas Electronics disclaims any and all liability for any malfunctions, failure or accident arising out of the use of Renesas Electronics products outside of such specified ranges.
9. Although Renesas Electronics endeavors to improve the quality and reliability of Renesas Electronics products, semiconductor products have specific characteristics, such as the occurrence of failure at a certain rate and malfunctions under certain use conditions. Unless designated as a high reliability product or a product for harsh environments in a Renesas Electronics data sheet or other Renesas Electronics document, Renesas Electronics products are not subject to radiation resistance design. You are responsible for implementing safety measures to guard against the possibility of bodily injury, injury or damage caused by fire, and/or danger to the public in the event of a failure or malfunction of Renesas Electronics products, such as safety design for hardware and software, including but not limited to redundancy, fire control and malfunction prevention, appropriate treatment for aging degradation or any other appropriate measures. Because the evaluation of microcomputer software alone is very difficult and impractical, you are responsible for evaluating the safety of the final products or systems manufactured by you.
10. Please contact a Renesas Electronics sales office for details as to environmental matters such as the environmental compatibility of each Renesas Electronics product. You are responsible for carefully and sufficiently investigating applicable laws and regulations that regulate the inclusion or use of controlled substances, including without limitation, the EU RoHS Directive, and using Renesas Electronics products in compliance with all these applicable laws and regulations. Renesas Electronics disclaims any and all liability for damages or losses occurring as a result of your noncompliance with applicable laws and regulations.
11. Renesas Electronics products and technologies shall not be used for or incorporated into any products or systems whose manufacture, use, or sale is prohibited under any applicable domestic or foreign laws or regulations. You shall comply with any applicable export control laws and regulations promulgated and administered by the governments of any countries asserting jurisdiction over the parties or transactions.
12. It is the responsibility of the buyer or distributor of Renesas Electronics products, or any other party who distributes, disposes of, or otherwise sells or transfers the product to a third party, to notify such third party in advance of the contents and conditions set forth in this document.
13. This document shall not be reprinted, reproduced or duplicated in any form, in whole or in part, without prior written consent of Renesas Electronics.
14. Please contact a Renesas Electronics sales office if you have any questions regarding the information contained in this document or Renesas Electronics products.

(Note1) "Renesas Electronics" as used in this document means Renesas Electronics Corporation and also includes its directly or indirectly controlled subsidiaries.

(Note2) "Renesas Electronics product(s)" means any product developed or manufactured by or for Renesas Electronics.

(Rev.5.0-1 October 2020)

## Corporate Headquarters

TOYOSU FORESIA, 3-2-24 Toyosu,  
Koto-ku, Tokyo 135-0061, Japan  
[www.renesas.com](http://www.renesas.com)

## Trademarks

Renesas and the Renesas logo are trademarks of Renesas Electronics Corporation. All trademarks and registered trademarks are the property of their respective owners.

## Contact information

For further information on a product, technology, the most up-to-date version of a document, or your nearest sales office, please visit:  
[www.renesas.com/contact/](http://www.renesas.com/contact/).